

07/2011 Top with asymmetric front ruffle

By: burda style magazine

<http://www.burdastyle.com/projects/072011-top-with-asymmetric-fr>



Top with asymmetric front ruffle burda style magazine patterns FAQ</a

Materials

Print chiffon

Step 1 — Preparation



Paper cut for ANSI A (German DIN A4) prints:

This pattern is printed on 8.5 × 11 sheets of plain paper. Do not scale or center pages before printing. Wait until all sheets are printed out before beginning to tape them together. **Do not cut out pattern pieces yet**— Arrange the sheets on a large, hard, flat surface so that they fit together, matching up like numbers and letters (i.e. 6A to 6A). To tape pattern together, fold under the margin of one piece (6A) and tape right against the line of it's matching number/letter (6A).

burda style magazine pattern do not have seam allowance included.

Seam and hem allowances to be added: Seams and edges 1.5 cm (5/8 in).

see example here: <http://www.burdastyle.com/projects/072011-jumpsuit/instructions/1>

Step 2 — Cutting out



Chiffon:

21right front 1x

22left front 1x

23back, on a fold 1x

a) 2 bias binding strips for armholes, 46 $\hat{=}$ 48 $\hat{=}$ 49 $\hat{=}$ 51 $\hat{=}$ 52 cm (181/8 $\hat{=}$ 19 $\hat{=}$ 191/4 $\hat{=}$ 201/4 $\hat{=}$ 201/2 ins) long, 4.5 cm (17/8 ins) wide (incl. allowances),

b) bias binding strip for back neck edge, 29 $\hat{=}$ 29 $\hat{=}$ 30 $\hat{=}$ 30 $\hat{=}$ 31 cm (111/2 $\hat{=}$ 111/2 $\hat{=}$ 12 $\hat{=}$ 12 $\hat{=}$ 121/4 ins) long, 4.5 cm (17/8 ins) wide (incl. allowances).

Satin:

c) hem band, 113 $\hat{=}$ 118 $\hat{=}$ 123 $\hat{=}$ 128 $\hat{=}$ 133 cm (441/2 $\hat{=}$ 461/2 $\hat{=}$ 481/2 $\hat{=}$ 501/2 $\hat{=}$ 521/2 ins) long, 10 cm (4 ins) wide, finished width 5 cm (2 ins),

d) narrow band, 14 cm (51/2 ins) long, 2.5 cm (1 in) wide, finished width 1.2 cm (1/2 in).

Vilene Bias Tape/stay tape: Iron to wrong side of back neck edge and armhole edges. The chain stitch of the tape must lie on the garment piece, approx. 1 mm from the marked seam line.

Step 3 — Bind back neck edge

Trim away allowance at neck edge of back piece. Fold binding strip in half lengthwise and press, right side facing out. Pin folded binding strip to neck edge and stitch 7 mm (1/4 in) from fabric edge. Turn binding strip over edge to inside and baste over joining seam. Topstitch binding close to edge.

Step 4 — Bust darts

Stitch bust darts in fronts. Press darts down.

Step 5 — Zigzag stitching

On each front piece, neaten upper edge, from, marking (seam number 1), with closely spaced zigzag stitching: Press allowance to wrong fabric side. Work from right side to stitch along fold edge at a narrow, closely spaced zigzag setting. On inside, carefully trim allowance close to stitching. Then finish the vertical front edges with closely spaced zigzag stitch.

Step 6 — Band

Turn in one end of narrow band and press. Fold band in half lengthwise, right side facing in. Stitch along lengthwise edge. Turn band right side out and press. Baste open end of band to shoulder edge of left front (markings).

Step 7 — Shoulder

Stitch shoulder seams. Trim seam allowances to 7 mm (1/4 in) wide, neaten together, and press onto back.

Step 8 — Armholes

Bind armhole edges as for neck edge.

Step 9 — Side seams

Stitch side seams. Trim seam allowances, neaten together, and press onto back. Sew upper ends of seam allowances in place by hand.

Step 10 — Hem

Stitch hem band to lower edge of fronts and of back. Press seam allowances of joining seam and of other lengthwise edge onto band. Fold band lengthwise, right side facing in, and stitch across ends. Turn band right side out. Sew inside edge of band in place by hand.

Step 11 — Shoulder

Lay right front on left front, with right sides of both facing up. Pin marked stitching lines together and stitch from lower edge of hem band to marking. Stitch lower end of shoulder band under upper edge of right front, between marking and corner.

BurdaStyle

07/2011 Top with asymmetric front ruffle