

10/2010 Long Coat

By: burda style magazine

<http://www.burdastyle.com/projects/102010-long-coat>



Long Coat burda style magazine patterns FAQ

Materials

Loden cloth

Step 1 — Preparation

Trace the pattern pieces from the pattern sheet. Lengthen piece 2 as indicated. Trace front facing from piece 1 as a separate pattern piece.

The snap fasteners marked on piece 1 are for sizes 36. For sizes 38 — 44, mark the top fastener the same distance from upper edge as for size 36. The bottom snap is the same for all sizes.

Seam and hem allowances:

Seams and edges 1.5 cm (5/8 in), hem and sleeve hems 4 cm (15/8 ins) (flare sleeve hem allowances). Cut lining pieces with 1.5 cm (5/8 in) seam and hem allowances.

Step 2 — Cutting Out



Loden:

1 — front 2x

2 — front facing 2x

3 — back, on a fold 1x

4 — sleeve 2x

5 — collar, on a fold 2x

6 — back facing, on a fold 1x

7 — flap 2x

a) 2 binding strips, 19 — 19.5 — 20 — 20.5 — 21 cm (7 1/2 — 7 3/4 — 8 — 8 1/4 — 8 3/8 ins) long, 4 cm (1 5/8 ins) wide (incl. allowance).

Lining: piece 1 minus width of facing; piece 2 without pleat, minus neck facing, with 3 cm (1 1/4 in)

allowance for ease pleat at centre back, and on a fold; pieces 3 and 6,
b) 4 pocket pieces, each 19 — 19.5 — 20 — 20.5 — 21 cm (7 1/2 — 7 3/4 — 8 — 8 1/4 — 8 3/8 ins) wide , 20 cm (8 ins) long (incl. allowance).
Interfacing: See pattern layout. Also interface hem allowances.

Step 3 — Stitch front and back darts

Stitch front and back darts. Press toward centre front or centre back.

Step 4 — Inverted pleat at centre back

To form inverted pleat, fold back piece along centre back, right side facing in, so that pleat lines meet. Stitch pleat from upper edge to arrow mark. Lay pleat in arrow direction and baste to upper edge. Press pleat the length of the seam but do not press folds below seam. Stitch fronts to back (seam number 1). Stitch shoulder seams and facing seams.

Step 5 — Facing right sides, collar pieces

Pin facing right sides together with jacket. Stitch along front and neck edges, to markings. Leave facing lying right sides together with jacket for now. Stitch collar pieces right sides together along outer edges, building a little extra fullness into top collar and beginning and ending stitching exactly on seam line of joining edge. Turn collar right side out. Lay collar between jacket and facing. Stitch undercollar to neck edge of jacket and stitch top collar to facing. Press seam allowances open. Turn facing to inside. Pin collar joining seams together exactly. Lay back facing up and stitch seam allowances together, close to collar joining seam. Lay facing down.

Step 6 — Hem

Unfold facings at hem. Press hem allowance to inside and sew in place by hand. Lay facings to inside again, and sew to hem allowance.

Step 7 — Sleeves

Stitch sleeve seams. Hem sleeves. Set in sleeves, easing sleeve caps and matching sleeve seam to lower marking on front.

Step 8 — Line jacket

On back lining piece, stitch ease pleat at upper edge, 5 cm (2 ins) long. Press pleat to one side. Hem back lining piece so that it is about 2 cm (3/4 in) shorter than jacket. Stitch darts and seams of lining. Set in sleeve linings. Stitch lining to inside edge of facing, leaving about 8 cm (3 1/4 ins) open at bottom edge. Lay lining inside jacket with wrong sides facing, pulling linings into sleeves. Pin a fold, about 1 cm (3/8 in) deep, in front lining pieces, above jacket hem. Turn in lining and sew to hem allowance of fronts by hand. Remove pins and press extra length of lining down. Sew remaining front edges of lining in place. Pin a fold, about 1 cm (3/8 in) deep, in sleeve linings above hems. Turn in sleeve linings and sew to hem allowances. Lay extra length of lining down and press.

Step 9 — Snaps

Cover top halves of snaps with lining. Sew top halves of snaps to inside of right front edge as marked. Sew bottom halves of snaps to left front. Take even, regular stitches and exit needle on both outside and inside of fabric.

BurdaStyle

10/2010 Long Coat