

08/2010 Oversized Vest

By: burda style magazine

<http://www.burdastyle.com/projects/082010-oversized-vest>

Oversized Vest burda style magazine patterns FAQ

Materials

Flannel

Step 1 — Preparation

Trace pattern pieces from the pattern sheet. Trace the facing from piece 1 as a separate pattern \hat{A} -piece.
Front lining piece: Mark a horizontal line from section seam to point of dart and cut open. Lay vertical dart closed and glue horizontal edges together at bottom end of dart. This creates a bust dart for the lining piece (see pattern layout).

Seam and hem allowances:

Seams and edges 1.5 cm (5/8 in), hem 4 cm (15/8 ins), no allowance at horizontal edges of centre fronts (scissors symbol) but 1.5 cm (5/8 in) allowance at dart. Cut lining pieces with 1.5 cm (5/8 in) seam and hem allowances.

Step 2 — Cutting Out



Flannel:

1— front 2x

2— front facing 2x

3— back 2x

4— side piece 2x

5— back facing, on a fold 1x

6— collar, on a fold 2x

7— collar band, on a fold 2x

8— front armhole facing 2x

9— back armhole facing 2x

a) 4 binding strips, 19 cm (7 1/2 ins) long, 3 cm (1 1/4 ins) wide (incl. allowance),

b) 2 pocket pieces, 19 cm (7 1/2 ins) wide, 10 cm (4 ins) long (incl. allowance),

c) 4 flap pieces, 15.5 cm (6 1/4 ins) long, 6 cm (2 3/8 ins) wide.

Lining: piece 1 as listed under Preparation for style 125; piece 2 minus neck facing and at centre back with an ease pleat of about 2 cm (3/4 in); piece 3 and also pocket pieces (piece b).

Interfacing: See pattern layout. Also interface hem allowances.

Step 3 — Stitch bust darts

Stitch bust darts. Cut close to end of seam at lower horizontal edge of fronts. Press dart allowances open, pressing points of darts flat. Lay horizontal edges of fronts together and baste together with herringbone stitch. Stitch side pieces to fronts.

Step 4 — Bound pockets with flaps

Mark an abutting line for binding, 7 mm (1/4 in) from joining lines (= finished width of binding). Hand baste along these lines to make them visible on right side of fabric. Fold binding strips lengthwise and press, wrong side facing in. Lay doubled binding strips on front and side pieces and pin so that fold edges of binding meet abutting lines. Stitch binding in place along joining lines, 7 mm (1/4 in) from fold edges. Slash between lines of stitching and clip diagonally toward ends of seams, but do not cut into binding. Press binding into pocket openings. Fold small fabric triangles at pocket opening ends to inside and stitch to binding, across base of each. Stitch each interfaced flap piece to flap piece with no interfacing, right sides together, rounding off corners. Leave joining edge open. Trim seam allowances. Turn flaps right side out and press. Slip joining edge of flaps to inside, through pocket openings, and stitch to seam allowances, close to upper binding joining seam. Stitch pocket lining pieces to seam allowances of lower binding and stitch fabric pocket pieces to seam allowances of flaps and upper binding. Trim pocket pieces even and stitch together.

Step 5 — Back and shoulder seams

Stitch centre back seam and back section seams. Stitch shoulder seams on jacket and facing. Press seams open.

Step 6 — Notched collar and front edges

Pin facing right sides together with jacket. Build a little extra fullness into corners of lapels. Stitch facing to hem edges, front edges, and edges of lapels, to marking. Leave facing lying right sides together with jacket for now. Stitch collar band pieces to collar pieces. Trim seam allowances. Press seams open. Topstitch close to each side of seams. Stitch collar pieces together on outer edges, building a little extra fullness into top collar. Begin and end stitching in front, exactly on seam line of joining edge. Turn collar right side out. Lay collar between jacket and facing. Stitch undercollar to neck edge of jacket and stitch top collar to facing. Press seam allowances of collar joining seams open. Turn facing to inside. Pin collar joining seams together exactly. Lay back facing up and stitch seam allowances together, close to collar joining seam. Lay back facing down.

Step 7 — Hem

Press hem allowance to inside and sew in place by hand.

Step 8 — Stitch allowances of centre seam on back lining together

Stitch allowances of centre seam on back lining together, 1 cm (3/8 in) from edge. For the ease pleat, stitch at top and bottom, each about 5 cm (2 ins) long, and baste in between. Press pleat to one side. Stitch darts and seams of lining.

Step 9 — Stitch lining to inside edges of facing

Stitch lining to inside edges of facing, leaving about 5 cm (2 ins) open at bottom. Lay lining inside waistcoat with wrong sides facing. Baste to armhole edges. Pin a fold, about 1 cm (3/8 in) deep, in lining above hem. Turn in lining and sew to hem allowance by hand. Lay extra length of lining down and press. Sew remaining front edges of lining to facings.

Step 10 — Stitch shoulder seams and side seams of armhole facings

Stitch shoulder seams and side seams of armhole facings. Neaten inside edges of facings. Stitch facings right sides together with armhole edges. Trim seam allowances. Lay facings into armholes, over seam allowances, and stitch to seam allowances, close to seam. Turn facings to inside. Press edges. Sew inside facing edges to lining.

BurdaStyle

08/2010 Oversized Vest