

07/2011 Shorts

By: burda style magazine

<http://www.burdastyle.com/projects/072011-shorts>



Shorts burda style magazine patterns FAQ

Materials

Sweatshirting


Step 1 — Preparation

Trace the pattern pieces from the pattern sheet. Follow lines and details for style 109.

Seam and hem allowances:

Seams and edges 1.5 cm (5/8 in).

Step 2 — Cutting out



2 front shorts piece 2x

3 back shorts piece 2x

4 pocket piece 4x

a) waistband, 82 â— 85 â— 89 â— 93 â— 97 cm (32 1/2 â— 33 1/2 â— 35 â— 36 3/4 â— 38 1/4 ins) long, 6 cm (2 1/2 ins) wide, finished width 3 cm (1 1/4 ins),

b) 2 binding strips for hem and slit edges, 68 â— 72 â— 75 â— 79 â— 82 cm (26 3/4 â— 28 1/2 â— 29 3/4 â— 31 1/4 â— 32 1/2 ins) long, 2.5 cm (1 in) wide (incl. allowances).

Step 3 — Side seams

Stitch side seams from upper edges to marking (seam number 1) â— do not stitch across pocket openings.

Press seam allowances open

Step 4 — In-seam pockets

Pin pocket pieces right sides together with seam allowances of pocket opening edges and stitch in place, directly along marked seam lines. Above pocket openings, stitch pocket pieces in place, close to seam. Press pocket pieces forward and stitch together. Baste upper pocket edges in place. Stitch a few stitches across each pocket opening end.

Step 5 — Legs

Stitch inside leg seams, beginning and ending exactly at hem line. Pull one shorts leg into the other, right sides facing. Stitch centre front and back seams as continuous seam. Press seam open, from upper edges to beginnings of curve. Do not press seam allowances flat along curve.

Step 6 — Waistband

Pin ends of waistband right sides together. Stitch seam on outer half of waistband, leaving inside half open, to insert elastic. Press seam allowances open. Fold waistband in half lengthwise and press, wrong side facing in. Stitch waistband edges together to upper edge of shorts, matching seam of waistband to centre back seam. Neaten seam allowances and press down. Pull elastic into waistband. Sew ends of elastic together for a circumference of 74 — 78 — 82 — 86 — 90 cm (29 1/4 — 30 3/4 — 32 1/2 — 34 — 35 1/2 ins).

Step 7 — Hem

At hem and slit edges, trim away allowances up to 1 cm (3/8 in) below top of slit. Iron fusible web tape along one long edge on wrong side of each binding strip. Turn under edge of fabric next to ironed-on tape, 1 cm (3/8 in) wide, and press. Unfold binding strips again. Peel off the paper backing. Lay right sides of edges of slits and hem on fusible web tape, so that edge of shorts meets pressed fold. Iron edges of shorts to tape, trimming away extending ends at slits. Turn binding over edges to inside and baste. Working from the outer side, edgestitch binding in place. Trim inside edge of binding close to stitching.

BurdaStyle

07/2011 Shorts