

01/2011 Babydoll Style Double Breasted Coat

By: burda style magazine

<http://www.burdastyle.com/projects/012011-babydoll-style-double->



Short coat burda style magazine patterns FAQ

Materials

natt

Step 1 — Preparation

Größen, Tailles, Sizes						2		3		4		
1	N		L		K		Oberweite Tour de poitrine Bust		Tailleweite Tour des taille Waist		Hüftweite Tour des hanches Hip	
	5'6" 168 cm		5'9" 176 cm		5'3" 160 cm		ins	cm	ins	cm	ins	cm
	US	Eur.	US	Eur.	US	Eur.						
	6	32	6	64	6	16	30	76	23	58	32 ½	82
	8	34	8	68	8	17	31 ½	80	24 ½	62	34	86
	10	36	10	72	10	18	33	84	26	66	35 ½	90
	12	38	12	76	12	19	34 ½	88	27 ½	70	37	94
	14	40	14	80	14	20	36 ½	92	29 ½	74	38 ½	98
	16	42	16	84	16	21	37 ½	96	30 ½	78	40 ½	102
	18	44	18	88	18	22	39 ½	100	32 ½	82	41 ½	106
	20	46	20	92	20	23	41	104	34	86	43 ½	110
	22	48	22	96	22	24	43 ½	110	36 ½	92	45 ½	116
	24	50	24	100	24	25	45 ½	116	38 ½	98	48	122
	26	52	26	104	26	26	48	122	41	104	50 ½	128
	28	54	28	108	28	27	50 ½	128	43 ½	110	52 ½	134
	30	56	30	112	30	28	52 ½	134	45 ½	116	55 ½	140
	32	58	32	116	32	29	55 ½	140	48	122	57 ½	146
	34	60	34	120	34	30	57 ½	146	50 ½	128	60	152

Trace the pattern pieces from the pattern sheet. Follow lines and details for style 118. Trace pocket \hat{A} -piece from piece 3 as a separate pattern piece \hat{a} — it is the same for all sizes.

The buttons marked on piece 1 are for size 17. For the other sizes, move front buttons up or down the same distance from corresponding size lines. Remark side buttons in same manner.

Seam and hem allowances:

Seams and edges 1.5 cm (5/8 in), \hat{A} -sleeve hems 4 cm (15/8 ins), lining 1.5 cm (5/8 in)

Step 2 — Cutting out



Natt:

1 front yoke 2x

2 back yoke 2x

3 front 2x

4 — pocket piece 2x

4 back, on a fold 1x

5 upper sleeve 2x

6 under sleeve 2x

7 collar, on a fold 2x

8 collar band, on a fold 2x

9 back facing, on a fold 1x

Lining: pieces 1 and 3 minus width of facing; piece 2 minus neck facing and with an ease pleat of about 2 cm (3/4 in) at centre back; pieces 4, 5, and 6; and also pocket pieces (piece 3).

Interfacing: See pattern layout. Also interface hem allowances.

Step 3 — Yoke

Stitch centre back seam of back yoke. Gather upper edge of coat back between asterisks. Gather upper edges of coat front pieces. Stitch yokes to fronts and to back (seam numbers 1 and 2). Press seam allowances onto yokes.

Step 4 — Shoulder seams

Stitch shoulder seams. Stitch side seams, but do not stitch across pocket openings.

Step 5 — In-seam pockets

Pin pocket pieces right sides together with seam allowances of pocket opening edges to pocket lining pieces in front and pocket pieces of coat fabric in back. Stitch pocket pieces in place, directly along marked seam lines. Press pocket pieces forward and stitch together.

Step 6 — Self-facings

Unfold self-facings on both fronts and stitch to back facing piece. Stitch facing to neck edge, from front edges (fold) to centre front. Leave facing lying right sides together with coat for now.

Step 7 — Collar

Stitch collar band pieces to collar pieces (seam number 5). Trim seam allowances and press open. Topstitch close to each side of seams. Lay collar pieces right sides together. Stitch along outer edges from seam number 6, beginning and ending stitching exactly at seam line of joining edge. Trim seam allowances. Turn collar right side out and press. Lay collar between coat and facing. Stitch undercollar to neck edge of coat and stitch top collar to facing. Press seam allowances open. Turn facing to inside. Pin collar joining seams together. In back, lay facing up again and stitch allowances together, close to collar joining seam.

Step 8 — Hem

Unfold facings at hem. Press hem allowance to inside but do not yet sew in place.

Step 9 — Hem allowance

Stitch sleeve seams. Press sleeve hem allowances to inside and sew in place by hand.

Step 10 — Sleeve caps

Set in sleeves, easing sleeve caps.

Step 11 — Back yoke lining

On back yoke lining, stitch allowances of centre seam together 1 cm (3/8 in) from edge. To form the ease pleat, stitch along centre back, from upper edge down about 5 cm (2 ins) long, then baste along centre back, to hem edge. Press pleat to one side. Undo basting. Stitch seams of lining. Set in sleeve linings.

Step 12 — Line coat, hem

Stitch lining to inside edges of facing, laying hem allowance down. Lay lining inside coat with wrong sides facing, pulling linings into sleeves. Turn hem allowance to inside and sew in place by hand. Turn in lining along hem edge, press fold edge lightly, push upward in a shallow curve, and pin to hem allowance. Sew

lining in place. Lay extra length of lining down and press lightly. Turn in sleeve lining and sew to sleeve hem allowance. Lay extra length down and press.

Step 13 — Snaps

Sew top halves of snap fasteners to inside of right front yoke, 2 cm (3/4 in) from front edge and level with button markings. Lay coat closed, matching centres. Sew bottom halves of snaps to left front yoke. Sew buttons to right front yoke as marked. Work a horizontal buttonhole in upper corner of left front yoke, for inside button. Sew button to inside of right yoke to match.

BurdaStyle

01/2011 Babydoll Style Double Breasted Coat