

12/2011 Plus Size Sequin Jacket

By: burda style magazine

<http://www.burdastyle.com/projects/122011-plus-size-sequin-jacket>



Sequin jacket burda style magazine patterns FAQ

Materials

Sequin fabric

Step 1 — Preparation




Paper cut for ANSI A (German DIN A4) prints:

This pattern is printed on 8.5 × 11 sheets of plain paper. Do not scale or center pages before printing. Wait until all sheets are printed out before beginning to tape them together. **Do not cut out pattern pieces yet**— Arrange the sheets on a large, hard, flat surface so that they fit together, matching up like numbers and letters (i.e. 6A to 6A). To tape pattern together, fold under the margin of one piece (6A) and tape right against the line of it's matching number/letter (6A).

burda style magazine pattern do not have seam allowance included.
Seam and hem allowances to be added: Seams and edges 1.5 cm (5/8 in).

Step 2 — Cutting out



Note: Place the paper pattern piece for the front on the fabric, with the front edge on the side edge of the sequined surface. Cut the 3 cm (1 1/4 in) wide allowance on the front edge from plain edge of the fabric. Also cut the facing strips a, b, and c from the plain edge of the fabric.

1 front 2x

2 back, on a fold 1x

3 sleeve 2x

a) facing strip for neck edge, 58 — 59 — 60 — 61 — 62 cm (23 — 23 1/4 — 23 3/4 — 24 — 24 1/2 ins) long, 5 cm (2 ins) wide (incl. allowances),

b) facing strip for lower edge, 116 — 120 — 126 — 132 — 138 cm (45 3/4 — 47 1/4 — 49 3/4 — 52 — 54 1/2 ins) long, 5 cm (2 ins) wide (incl. allowances),

c) 2 facing strips for lower sleeve edges, 34 — 34 — 35 — 35 — 36 cm (13 1/2 — 13 1/2 — 13 3/4 — 13 3/4 — 14 1/4 ins) long, 5 cm (2 ins) wide (incl. allowances).

Interfacing: Iron strips of interfacing, approx. 1 cm (3/8 in) wide, to wrong side of front shoulder seam edges and to wrong side of neck and armhole edges so that strips lie on garment piece, 2 mm (a scant 1/8 in) past seam lines.

Step 3 — Bust darts

Stitch bust darts. Press darts down.

Step 4 — Shoulder seams

Stitch shoulder seams (seam number 1). Press seam allowances onto back. Cut pre-pressed bias tape apart along centre — it is then 1 cm (3/8 in) wide when folded double. Unfold bias tape and pin to edge of seam allowance. Stitch 5 mm (3/16 in) from edge. Then fold bias tape over allowance edge and pin in place, without turning edge under. Work from upper side to stitch binding close to joining seam, thereby catching opposite edge.

Step 5 — Sleeves

Stitch sleeves to fronts and back (seam numbers 2 and 3). Press allowances of sleeve joining seams onto fronts and back. Bind seam allowances with bias tape together.

Step 6 — Side seams

Stitch side seams and sleeve seams as continuous seams. Press seam allowances onto back. Bind allowances.

Step 7 — Front

On front edges, fold edges of allowances under to half width. Fold doubled allowances to outside and pin to neck and lower edges.

Step 8 — Facing strip

Fold facing strips for neck edge and edges lengthwise, right side facing out. Press, shaping neck edge strip to match neck edge by stretching the fold edge and easing the open edges. Pin doubled facing strips to neck and lower edges so that fold edge of each strip lies on garment piece, 1.5 cm (5/8 in) past seam line, and ends lie on allowances of front edges. Trim ends of strips. Stitch strips in place. Trim seam allowances, trimming corners diagonally. Turn facing strips and allowances on front edges to inside. Sew inside edges in place by hand.

Step 9 — Facing strips

Fold facing strips for sleeves in half lengthwise and press. Turn in one end of each strip. Working from right side, stitch doubled strip to lower edge of sleeve so that fold edge of strip lies on garment piece, 1.5 cm (5/8 in) wide, and open end of strip lies on turned-under end. Turn strips to inside. Sew inside edges in place by hand.

BurdaStyle

12/2011 Plus Size Sequin Jacket