

04/2011 Flared Trousers

By: burda style magazine

<http://www.burdastyle.com/projects/042011-flared-trousers>



Flared Trousers burda style magazine patterns FAQ</a

Materials

broderie anglaise with border and scalloped edge on one edge

Step 1 — Preparation

Trace the pattern pieces from the pattern sheet. Note different grain lines for views A, B, and C. Lengthen pieces 21 and 22 as indicated.

The stitching line at the zip slit is marked for size 36. For sizes 38 — 44, mark the stitching line the same distance from centre front as for size 36, noting length of slit. The pocket lines on piece 22 are marked in full for size 36 only. For the other sizes, complete these lines accordingly.

Seam and hem allowances:

Seams and edges 1.5 cm (5/8 in). Views B, C: hem 4 cm (15/8 ins). For view A, place the lower edges of the paper pattern pieces on the scalloped edge of the broderie anglaise.

Step 2 — Cutting out



21 front trouser piece 2x

22 back trouser piece 2x

23 pocket piece, front pocket 4x

— (twice just to lining line)

a) left underlap piece, 11 — 11 — 11 — 13 — 13 cm (43/8 — 43/8 — 43/8 — 51/4 — 51/4 ins) long, 5 cm (2 ins) wide, finished width 2.5 cm (1 in),

b) 2 bias welt strips (front —pockets), 15 cm (6 ins) long, 7 cm (23/4 ins) wide —(incl. allowances),

c) bias binding strip (back pocket), 13 cm (51/4 ins) long, 4 cm (15/8 ins) wide (incl. allowances),

d) 2 bias binding strips (back pocket), 13 cm (51/4 ins) wide, 13 cm (51/4 ins) long (incl. allowances),

e) right waistband, 40.5 — 42.5 — 44.5 — 46.5 — 48.5 cm (16 — 163/4 — 171/2 —

18 1/4 — 19 1/8 ins) long, left waistband with 3 cm (1 1/4 in) underlap, 43.5 — 45.5 — 47.5 — 49.5 — 51.5 cm (17 1/8 — 18 — 18 3/4 — 19 1/2 — 20 3/8 ins) long, each 9 cm (3 1/2 ins) wide, finished width 4.5 cm (1 3/4 ins),

f) 6 belt carriers, a total of 54 cm (21 1/4 ins) long, 4 cm (1 5/8 ins) wide (incl. allowances).

Interfacing: See pattern layout. Iron strips of interfacing, about 4 cm (1 5/8 ins) wide, to wrong side of front and back pieces, over pocket markings.

Step 3 — Darts

Stitch back darts and press toward centre back.

Step 4 — Welt pocket

Sew single welt pockets on front trouser pieces: Mark an abutting line 2 cm (3/4 in) from each welt joining line (= finished width of welt). Fold welt strips lengthwise, right side facing out, and press. Baste each folded welt strip over welt joining line so that fold edge of welt meets abutting line and open long edges lie between pocket lines. Stitch welt in place along welt joining line. Stitch larger pocket pieces to pocket piece joining lines. Slash between lines of stitching and clip diagonally toward ends of seams, not cutting into welt or pocket pieces. Turn welt into pocket opening and pull pocket piece to inside. Stitch remaining pocket pieces to seam allowances of welt joining seams. Fold small triangles at pocket opening ends to inside and stitch to welt and pocket pieces, from seam end to seam end. Stitch pocket pieces together.

Step 5 — Welt pocket

Sew single welt pocket on right trousers back as described for trouser fronts. Mark abutting line for welt 7 mm (1/4 in) from welt joining line. Before stitching pocket pieces together, work a vertical buttonhole in centre of pocket, 1 cm (3/8 in) below welt joining seam, catching pocket piece which is stitched to welt. — Stitch side seams and inside leg seams Press seam allowances open. Sew bottom ends of seam allowances in place by hand. Stitch centre front seam from slit mark to inside leg seam.

Step 6 — Zip slit

Press self-facings on slit edges to inside. Stitch along centre front on the right and 5 mm (3/16 in) before centre front on the left. Stitch zip under left slit edge (underlap), stitching close to teeth of zip. Pin slit closed, matching center fronts. Stitch loose zip tape to right facing, not catching trouser piece. Baste facing in place. Topstitch slit from upper edge to 3 cm (1 1/4 ins) above the end, as marked. Fold underlap piece lengthwise and stitch across bottom end. Turn right side out. Lay underlap under left edge of opening and pin to facing. Stitch facing to underlap, close to zip joining seam. Lay slit closed again and topstitch to the end, catching underlap.

Step 7 — Belt carriers

Fold strip for belt carriers lengthwise, right side facing in. Stitch 1 cm (3/8 in) from fold edge. Turn right side out. Topstitch close to edges. Cut into 6 equal pieces. Baste belt carriers to upper edge of trousers, placing one each at centre of front trouser pieces, 5 cm (2 ins) from each side seam, and on each trousers back, 1 cm (3/8 in) from centre seam.

Step 8 — Waistband and centre back seam

Stitch right and left waistband to upper edge of trousers, stitching waistband underlap to underlap of slit. Press seam allowances of joining seams onto waistband pieces. Fold waistband pieces in half lengthwise and press, wrong side facing in. Unfold waistband again. Attach hook of fastener to inside half of waistband, 1 cm (3/8 in) from right front end. Fold waistband pieces lengthwise, right side facing in, and stitch across front ends. Turn right side out. Stitch centre back seam, stitching ends of waistband together. Press seam allowances open, from upper edge to beginning of curve. Do not press seam allowances flat along curve. Turn in inside edge of waistband and baste over joining seam. Work from right side of garment to stitch along line of seam. Attach bar of fastener to waistband, to match hook.

Step 9 — Belt carriers

Turn belt carriers up, turn ends in, and stitch to upper edge of waistband.

BurdaStyle

04/2011 Flared Trousers