

# 10/2011 Long Sweater Coat with Tie

By: burda style magazine

<http://www.burdastyle.com/projects/102011-long-sweater-coat-with>

---



Coat with belt burda style magazine patterns FAQ

## Materials

Bulky-style knit fabric with horizontal pattern

---

## Step 1 — Preparation



This pattern is printed on 8.5 × 11 sheets of plain paper. Do not scale or center pages before printing. Wait until all sheets are printed out before beginning to tape them together. **Do not cut out pattern pieces yet**— Arrange the sheets on a large, hard, flat surface so that they fit together, matching up like numbers and letters (i.e. 6A to 6A). To tape pattern together, fold under the margin of one piece (6A) and tape right against the line of it's matching number/letter (6A).

**burda style magazine pattern do not have seam allowance included.**  
Seam and hem allowances to be added: Seams and edges 1.5 cm (5/8 in).

---

## Step 2 — Cutting out



**Knit fabric:**

21 front with integrated collar 2x

â—’â—’pocket piece 2x

22 back, on a fold 1x

23 sleeve 2x

24 front facing

â—’â—’with integrated collar 2x

**Leather:**

tie belt, a total of 164 â— 168 â— 172 â— 176 â— 180 cm (64 1/2 â— 66 1/4 â— 67 3/4 â— 69 1/4 â— 71 ins) long, 5 cm (2 ins) wide (incl. allowances).

Vilene Bias Tape/ stay tape: Iron to shoulder seam edge, front edges and collar edges of fronts, to back neck edge, and to armhole edges.

### Step 3 — Belt carriers

For the two belt carriers, cut 16 cm (6 3/8 ins) of twill tape and fold lengthwise. Edgestitch long edges together. Cut into two equal pieces. Lay in loops and pin ends together. Pin belt carriers to the fronts, at marked side seam line, between markings.

### Step 4 — Inseam pockets

Pin the pocket pieces right sides together with seam allowances of back piece, matching markings. Stitch pocket pieces to seam allowance, 5 mm (3/16 in) from seam line. Turn pocket pieces over joining seam and

press. On each front pocket opening edge, pin a piece of twill tape, 18 cm (7 ins) long, to seam allowance 5 mm (3/16 in) from seam line. Stitch in place with small zigzag stitching. Stitch the side seams but do not stitching across the pocket openings. Press the seam allowances open and press the pocket opening edges. Sew inner edge of twill tape to inside of front, with small stitches by hand. Turn pocket pieces forward and baste to wrong side of fronts. To stitch the pocket pieces in place, pin the paper pattern piece to the coat front and stitch along its edge.

---

## **Step 5 — Darts**

Cut darts on fronts along centre, approx. 5 cm (2 ins) long. Stitch the shoulder seams (seam number 1). On the integrated collar pieces of the fronts, stitch the centre back seam. Press the seam allowances open. Work from centre back to stitch the collar to the neck edge of the coat, and go on to stitch the darts. Press seam allowances open. Press darts forward.

---

## **Step 6 — Lower edges**

Trim away allowances on lower edges of front facings. Neaten the edge. Trim away allowance on inner edge of facings. Bind the edge with twill tape.

---

## **Step 7 — Collar**

On the integrated collar of the facings, Stitch the centre back seam. Pin facing right sides together with fronts and pin collar edges together. Stitch along front edges and edges of collar. Turn facing to inside and turn collar right side out. Baste inside edge of collar over joining seam. Work from outside of garment to stitch along line of back joining seam. Sew inside edge of facing to shoulder seams. Stitch twill tape over seam allowances of collar joining seam, turning ends of tape under.

---

## **Step 8 — Hem**

Baste lower facing edges in place — hem allowance extends. Lay twill tape on hem allowance, 5 mm (3/16 in) from hem line, and stitch in place with zigzag stitching. Turn in extending ends of tape. Turn hem allowance with twill tape to inside and sew in place by hand.

---

## **Step 9 — Twill tape**

Pin twill tape to hem allowance on lower edge of each sleeve, 5 mm (3/16 in) from hem line. Stitch in place with small zigzag stitching. Stitch sleeve seams. Press seam allowances open. Turn sleeve hem allowances with twill tape to inside and sew in place by hand.

---

## **Step 10 — Sleeve caps**

Set in sleeves, easing sleeve caps.

---

## **Step 11 — Tie belt**

Stitch belt pieces together to form one long strip. Fold lengthwise edges to wrong side, 1.2 cm (1/2 in) wide, and adhere with glue stick. Fold belt in half lengthwise. Edgestitch open fold edges together.

---

**BurdaStyle**

10/2011 Long Sweater Coat with Tie