

# 10/2010 Double-breasted Jacket

By: burda style magazine

<http://www.burdastyle.com/projects/102010-double-breasted-jacket>

---



Double-breasted Jacket burda style magazine patterns FAQ

## Materials

Crushed wool twill

---

## Step 1 — Preparation

Trace the pattern pieces from the pattern sheet. Trace facing from piece 1 as a separate pattern piece. The welt joining line on pattern piece 1 is marked for size 36. For sizes 38 — 44, mark the joining line according to the size lines. The pocket always begins 1.5 cm (5/8 in) before the dart. The buttonholes on piece 4 are marked for size 36. Remark the buttonholes for the other sizes accordingly.

The lapel buttonhole on piece 1 is marked for size 36. For sizes 38 — 44, remark the buttonhole according to the size lines.

Front lining piece: Trace the front as a separate pattern piece, to the facing line. Mark a horizontal line from section seam to point of dart and cut open. Lay vertical darts closed and glue horizontal edges together at bottom end of dart. This will create a bust dart for the lining piece (see pattern layout).

Seam and hem allowances:

Seams and edges 1.5 cm (5/8 in), no allowance on horizontal edges of front (scissors symbol) but 1.5 cm (5/8 in) allowance at darts, hem and sleeve hems 4 cm (1 5/8 ins). Cut lining pieces with 1.5 cm (5/8 in) seam and hem allowances.

---

## Step 2 — Cutting Out



Top fabric:

1 front 2x

front facing 2x

2 back 2x

3 side piece 2x

4 upper sleeve 2x  
5 undersleeve 2x  
6 collar, on a fold 2x  
7 collar band, on a fold 2x  
8 back facing, on a fold 1x  
9 upper left welt 1x  
10 pocket piece (upper left pocket) 1x  
a) 2 welts (lower pockets), 15.5 — 16 — 16.5 — 17 — 17.5 cm (6 1/4 — 6 3/8 — 6 1/2 — 6 3/4 — 7 ins) long, 10 cm (4 ins) wide, finished width 5 cm (2 ins),  
b) 2 pocket pieces (lower pockets), 18.5 — 19 — 19.5 — 20 — 20.5 cm (7 1/4 — 7 1/2 — 7 3/4 — 8 — 8 1/4 ins) wide, 19 cm (7 1/2 ins) long (incl. allowance).  
Lining: piece 1 as listed under Preparation ; piece 2 minus neck facing and with an ease pleat of about 2 cm (3/4 in) at centre back; piece 4 without vent facing; and also pieces 3, 5, 10, and b.  
Interfacing: See pattern layout. Also interface hem allowances.

---

### Step 3 — Bust Darts

Stitch bust darts. Clip lower horizontal edge of fronts close to end of seam. Press dart allowances open, pressing points of darts flat. Lay horizontal edges of fronts together and baste with herringbone stitch. Stitch side pieces to fronts.

---

### Step 4 — Welt pockets

Welt pockets on fronts and upper pocket on left front: Fold welts lengthwise, right side facing in. Stitch across ends. Turn welts right side out. Stitch welts to fronts, at each marked joining line, right sides together — welts point down. Lay fabric pocket pieces on fronts opposite welts and stitch 1.5 cm (5/8 in) from welt joining seam. These seams should be about 7 mm (1/4 in) shorter at the ends than the welt joining seams. The seam on the slanted upper pocket must be 1 cm (3/8 in) shorter at the front end than the welt joining seam. Slash between lines of stitching and clip diagonally toward each last stitch. Do not cut into pocket pieces. Pull pocket pieces to inside and press welts over pocket openings. On the inside, stitch pocket lining pieces to seam allowances of welt joining seams. Fold small triangles at pocket opening ends to inside and stitch to pocket pieces. Trim pocket pieces even and stitch together. Sew narrow edges of welts in place by hand.

---

### Step 5 — Vent

Stitch centre back seam, leaving vent open at the bottom. Clip seam allowance of left back diagonally into corner at top of vent. Press seam allowances open and press allowances of vent onto right back. Press allowance on vertical edge of underlap on left back to inside. Topstitch right back diagonally as marked, catching underlap.

---

### Step 6 — Stitch shoulder seams on jacket and facing

Stitch shoulder seams on jacket and facing.

---

### Step 7 — Notched collar

Stitch collar band pieces to collar pieces. Trim seam allowances and press open. Topstitch close to each side of seams. Stitch collar pieces together along outer edges, building a little extra fullness into top collar and beginning and ending stitching exactly on seam line of joining edge. Turn collar right side out. Pin facings

right sides together with jacket. Pin lapel fold lines together. Pin upper edges together at marking (seam number 5). Build a little extra fullness into corners of lapels. Stitch along front edges and edges of lapels, up to marking. At marking, clip seam allowances of fronts and facing close to end of seams. Leave facings lying right sides together with jacket for now. Lay collar between jacket and facing. Stitch undercollar to neck edge of jacket, from marking to each corner. Clip seam allowance of fronts into corners. Stitch long edge of undercollar to neck edge of jacket. Stitch top collar to facing and clip seam allowance of facing into corners. Press seam allowances of collar joining seams open. Turn facing to inside. Pin collar joining seams together exactly. Lay back facing up and stitch seam allowances together, close to collar joining seam. Lay facing down again.

---

## **Step 8 — Stitch side pieces to back**

Stitch side pieces to back. At hem, turn back front facings and back vent facing. Press hem allowance to inside. Sew hem in place by hand. Lay facings to inside again.

---

## **Step 9 — Two-piece sleeve with sleeve vent**

Stitch front sleeve seams (seam number 7). On upper sleeves, lay vent facing and hem allowance outward. Mitre the corner. Trim allowances of mitring seam to 5 mm (3/16 in) wide and press open. Stitch hem allowance on undersleeves to lengthwise edge of underlaps, right sides together. Stitch back sleeve seams above vents. Turn hem allowances and vent facings to inside. Press edges of hem and vents to inside and press allowance on lengthwise edge of underlaps to inside. Work buttonholes for smaller buttons. On inside, stitch across facing and underlap at top of vent. Sew hems in place by hand.

---

## **Step 10 — Set in sleeves/shoulder pads**

Set in sleeves, easing sleeve caps. Sew in shoulder pads.

---

## **Step 11 — Sew lining**

On centre back lining pieces, stitch allowances of centre seam together above vent, stitching 1 cm (3/8 in) from edge. For the ease pleat, stitch along centre back at top and bottom (above vent), each about 5 cm (2 ins) long, and baste in between. Press pleat and vent allowances onto left back. Stitch darts and remaining seams of lining. Set in sleeve linings.

---

## **Step 12 — Line jacket**

Stitch lining to inside edge of facing, leaving about 7 cm (3 ins) open at bottom. Lay lining inside jacket, with wrong sides facing, pulling linings into sleeves. At back vent, turn in lining at edge of underlap on left back and pin. Trim other edge of lining to 1 cm (3/8 in) before hemmed edge of underlap. Clip 1 cm (3/8 in) diagonally into top corner. Turn in edge of lining and pin to vent facing of right back. Turn in lining and pin to underlap at top of vent. Pin a fold in lining about 1 cm (3/8 in) deep above jacket hem. Turn in lower edge of lining and sew to hem allowance. Lay extra length of lining down and press lightly. Sew remaining front edges of lining to facing. Sew lining to back vent.

---

## Step 13 — Sleeve linings

Pin lining seam to sleeve seam at top end of vent, pushing lining up slightly. At vent, turn back lining which lies on top. Turn in lining which lies below and pin to edge of underlap on undersleeve. Lay turned back lining over vent, trim to 1 cm (3/8 in) before edge of underlap, trim away 1 cm (3/8 in) below end of vent, and clip diagonally, about 1 cm (3/8 in) long, into corner. Turn in lining and pin to vent facing of upper sleeve and to underlap at top end of vent. Turn in lower edge of lining and pin to hem allowance. Sew lining in place. Stitch lining of other sleeve in place in same manner.

---

**BurdaStyle**

10/2010 Double-breasted Jacket