

11/2010 Coat with mandarin collar

By: burda style magazine

<http://www.burdastyle.com/projects/112010-coat-with-mandarin-co>



Coat with mandarin collar burda style magazine patterns FAQ

Materials

plaid wool fabric

Step 1 — Preparation

Größen, Tailles, Sizes						2		3		4		
1	N		L		K		Oberweite Tour de poitrine Bust		Tailleweite Tour des taille Waist		Hüftweite Tour des hanches Hip	
	5'6" 168 cm		5'9" 176 cm		5'3" 160 cm		ins	cm	ins	cm	ins	cm
	US	Eur.	US	Eur.	US	Eur.						
	6	32	6	64	6	16	30	76	23	58	32 ½	82
	8	34	8	68	8	17	31 ½	80	24 ½	62	34	86
	10	36	10	72	10	18	33	84	26	66	35 ½	90
	12	38	12	76	12	19	34 ¾	88	27 ¾	70	37	94
	14	40	14	80	14	20	36 ¾	92	29 ¾	74	38 ¾	98
	16	42	16	84	16	21	37 ¾	96	30 ¾	78	40 ¾	102
	18	44	18	88	18	22	39 ½	100	32 ½	82	41 ¾	106
	20	46	20	92	20	23	41	104	34	86	43 ½	110
	22	48	22	96	22	24	43 ½	110	36 ¾	92	45 ¾	116
	24	50	24	100	24	25	45 ¾	116	38 ¾	98	48	122
	26	52	26	104	26	26	48	122	41	104	50 ½	128
	28	54	28	108	28	27	50 ½	128	43 ½	110	52 ¾	134
	30	56	30	112	30	28	52 ¾	134	45 ¾	116	55 ¾	140
	32	58	32	116	32	29	55 ¾	140	48	122	57 ¾	146
	34	60	34	120	34	30	57 ¾	146	50 ¾	128	60	152

Trace the pattern pieces from the pattern sheet. Follow lines and details for style 127. Lengthen pieces 25, 27, and 28 as indicated. Trace the pocket piece from piece 27 as a separate pattern piece — it is the same for all sizes.

The buttonholes and buttons marked on piece 21 are for size 17. For sizes 18 — 21, mark the top buttonhole the same distance from neck edge as for size 17. The bottom buttonhole is the same for all sizes. Centre the other buttonhole in between. Remark the buttons to match.

Seam and hem allowances:

Seams and edges 1.5 cm (5/8 in), hem and sleeve hems 4 cm (15/8 ins), no allowance on upper edges of lower front and back. Cut lining pieces with 1.5 cm (5/8 in) seam and hem allowances.

Step 2 — Cutting out



Plaid fabric:

21 upper front 2x

22 upper back 2x

23 upper sleeve 2x

24 under sleeve 2x

25 front facing 2x

26 back facing, on a fold 1x

27 lower front 2x

28 — 28 — pocket piece 2x

28 lower back, on a fold 1x

29 standing collar, on a fold 2x

Lining: pieces 21 and 27 to lining line; piece 22 minus width of facing and with an ease pleat, about 2 cm (3/4 in) wide, at centre back; pieces 23, 24 and 28; and also the pocket piece.

Interfacing: See pattern layout. Also interface hem allowances.

Step 3 — Darts

Note: Since the seam allowances on lower edges of upper garment will be trimmed away, each of the following seams must be secured with backstitching at the marked lower edge: centre back seam, side seams, and dart seams.

Stitch centre seam and darts on upper back. Press centre seam allowances open. Press darts toward centre back. Stitch front darts. Trim dart allowances to 1 cm (3/8 in) wide and press open, pressing points of darts flat. Stitch side seams and shoulder seams of upper pieces.

Step 4 — Seam allowance

Trim away seam allowance on lower edge of upper garment. Pin lower edge of upper garment to upper edge of petersham ribbon, 7 mm (1/4 in) wide. Use a triple stitch to stitch 3 mm (1/8 in) from edge.

Step 5 — Sides

Stitch side seams on lower front and back pieces. Begin and end stitching 1 cm (3/8 in) below upper edge and backstitch to secure top ends of seams. Do not stitch across pocket openings, between markings.

Step 6 — In-seam pockets

Pin pocket pieces right sides together with seam allowances of pocket opening edges — pocket lining pieces in front, pocket pieces of main fabric in back. Stitch pocket pieces in place close to side seam and along line of seam on pocket opening edges. Press seams open, pressing pocket —pieces apart. Topstitch 7 mm (1/4 in) from front pocket opening edges and stitch horizontally at ends of pocket openings. Press pocket pieces forward and baste to wrong side of front. To stitch pocket pieces in place, pin paper pattern piece to front and topstitch along edges of pattern piece.

Step 7 — Front and back

Machine baste (longest stitch setting) between asterisks on lower front and back pieces, 7 mm and 15 mm (1/4 in and 5/8 in) from upper edge. Gather the fabric along these gathering threads to 7 cm (23/4 ins) wide on each front piece and to 6.5 cm (21/2 ins) wide on each back piece. Lay front and back pieces on petersham ribbon so that upper edges meet lower edge of upper garment and side seams match. Use a triple stitch to —stitch lower front and back pieces to petersham ribbon, stitching 1.3 cm (a generous 1/2 in) from edge. Trim edge to 3 mm (1/8 in) from stitching.

Step 8 — Front edges and collar

Stitch shoulder seams on facing. Pin facing right sides together with coat. Stitch along front edges and upper edges, to centre front. Trim seam allowances. Leave facing lying right sides together with coat for now. Lay collar pieces right sides together. Stitch together along front and upper edges, beginning and ending stitching —ing in front exactly on seam line of joining edge. Trim seam allowances. Turn collar right side out and press. Lay collar between coat and facing. Stitch outer collar piece to neck edge of coat and stitch inside collar piece to facing. Press seam allowances open. Turn facing to inside. Pin collar joining seams to —gether. Lay facing in back up again and stitch seam allowances together, close to collar joining seam. Lay facing down.

Step 9 — Sleeves

Stitch sleeve seams. Press sleeve hem allowances to inside and sew in place by hand.

Step 10 — Sleeve caps

Set in sleeves, easing sleeve caps. Sew shoulder pads in place.

Step 11 — Sew lining

On upper lining back, stitch allowances of centre seam together, 1 cm (3/8 in) from edge. Stitch along centre back to form the ease pleat, stitching about 5 cm (2 ins) long at top and bottom. Baste in between. Press pleat to one side. Stitch darts, side seams and shoulder seams on upper lining. Stitch side seams on lower lining pieces. Gather upper edges each between the asterisks. Stitch lower lining to upper lining. Set in sleeve linings.

Step 12 — Line coat, hem

Stitch lining to inside edges of facing, laying hem allowance down. Place lining inside coat with wrong sides facing, pulling linings into sleeves. Turn hem allowance to inside again and sew in place by hand. Turn in lining along lower edge of coat. Press fold edge lightly, push upward in a shallow curve, and pin to hem allowance. Sew facings and lining in place. Lay extra length of lining down and press lightly. Pin a fold, about 1 cm (3/8 in) deep, in lining, above sleeve hems. Turn in sleeve lining and sew to hem allowance. Lay extra length of lining down and press.

Step 13 — Buttonholes

Work buttonholes in right upper front piece. Work top and bottom buttonholes in upper left front, for inside buttons.

BurdaStyle

11/2010 Coat with mandarin collar