

02/2011 Bustier top with cap sleeves

By: burda style magazine

<http://www.burdastyle.com/projects/022011-bustier-top-with-cap-s>



Top with shoulder sleeve burda style magazine patterns FAQ

Materials

stretch tulle lace

Step 1 — Preparation

Größen, Tailles, Sizes						2		3		4		
1	N		L		K		Oberweite Tour de poitrine Bust		Tailleweite Tour des taille Waist		Hüftweite Tour des hanches Hip	
	5'6" 168 cm		5'9" 176 cm		5'3" 160 cm		ins	cm	ins	cm	ins	cm
	US	Eur.	US	Eur.	US	Eur.						
	6	32	6	64	6	16	30	76	23	58	32 ½	82
	8	34	8	68	8	17	31 ½	80	24 ½	62	34	86
	10	36	10	72	10	18	33	84	26	66	35 ½	90
	12	38	12	76	12	19	34 ½	88	27 ½	70	37	94
	14	40	14	80	14	20	36 ½	92	29 ½	74	38 ½	98
	16	42	16	84	16	21	37 ½	96	30 ½	78	40 ½	102
	18	44	18	88	18	22	39 ½	100	32 ½	82	41 ½	106
	20	46	20	92	20	23	41	104	34	86	43 ½	110
	22	48	22	96	22	24	43 ½	110	36 ½	92	45 ½	116
	24	50	24	100	24	25	45 ½	116	38 ½	98	48	122
	26	52	26	104	26	26	48	122	41	104	50 ½	128
	28	54	28	108	28	27	50 ½	128	43 ½	110	52 ½	134
	30	56	30	112	30	28	52 ½	134	45 ½	116	55 ½	140
	32	58	32	116	32	29	55 ½	140	48	122	57 ½	146
	34	60	34	120	34	30	57 ½	146	50 ½	128	60	152

Trace the pattern pieces from the pattern sheet.

Seam and hem allowances:

Seams and edges 1.5 cm (5/8 in), hem 4 cm (15/8 ins).

Step 2 — Cutting out



Tulle lace / stretch jersey:

21upper front, on a fold 1x

22centre lower front, on a fold 1x

23side lower front 2x

24upper back, on a fold 1x

25centre lower back, on a fold 1x

26side lower back 2x

Lining: pieces 21 and 24.

Interfacing: Iron Vilene Bias Tape/stay tape to neck and armhole edges of \hat{A} -lining pieces.

Step 3 — Lace pieces

Note: Stitch seams on stretch fabrics with a special stretch stitch or at a narrow zigzag setting.

Baste each tulle lace piece to respective jersey piece, with wrong side facing right side. Treat these pieces as one layer of fabric from now on.

Step 4 — Darts

Stitch front and back darts. Press darts toward centre. Stitch darts of lining.

Step 5 — Neck edge, armholes, and shoulder seams

Pin lining pieces right sides together with upper front and back. Stitch along neck and armhole edges, beginning and ending 2 cm (3/4 in) below each shoulder seam line. Trim seam allowances. Clip curves close to stitching. Turn lining of front (not back) to inside. Push front shoulder edges through the as-yet-unturned back shoulder edges, right fabric sides of front and back and of lining lie facing. Stitch shoulder seams of outer fabric and lining. Pull front (lying inside) slightly up and out and press seam allowances open. This will be easier if you slip the handle of a wooden spoon under the seams. Then stitch remaining open edges of neck edge closed. Pull front down out of back shoulder edges and the back lining will turn itself to the inside. Press neck edge.

Step 6 — Armhole

At right armhole, lay lining up. Stitch right side seam of outer fabric and lining as continuous seam. Press seam allowances open.

Step 7 — Front and back

Stitch section seams on lower front and back. Stitch right side seam. Stitch lower pieces to upper front and back, not catching lining. Press seam allowances open.

Step 8 — Hem

Press hem allowance to inside and sew in place by hand

Step 9 — Lining and zip

At left armhole, lay lining up again. Press allowances on left side edges to inside. Stitch zip under edges so that zip teeth are covered. Turn lining to inside again, turn edges under, and sew to zip tapes. Lay lower edge of lining flat over horizontal section seam, not turned under, and stitch to seam allowance, as far as possible. Sew remaining open edge of lining in place by hand

BurdaStyle

02/2011 Bustier top with cap sleeves