

# 07/2011 Net top

By: burda style magazine

<http://www.burdastyle.com/projects/072011-net-top>

---



Net top burda style magazine patterns FAQ

## Materials

Net fabric

---

## Step 1 — Preparation



Paper cut for ANSI A (German DIN A4) prints:

This pattern is printed on 8.5 × 11 sheets of plain paper. Do not scale or center pages before printing. Wait until all sheets are printed out before beginning to tape them together. **Do not cut out pattern pieces yet**— Arrange the sheets on a large, hard, flat surface so that they fit together, matching up like numbers and letters (i.e. 6A to 6A). To tape pattern together, fold under the margin of one piece (6A) and tape right against the line of it's matching number/letter (6A).


**burda style magazine pattern do not have seam allowance included.**

Seam and hem allowances to be added: Seams and edges 1.5 cm (5/8 in).

see example here: <http://www.burdastyle.com/projects/072011-jumpsuit/instructions/1>

---

## Step 2 — Cutting out



1 front, on a fold 1x

2 back, on a fold 1x

Water-soluble stabilizer: See pattern layout. Cut stabilizer pieces without seam allowances. Baste the pieces to front and back net fabric pieces to prevent the fabric edges from stretching while sewing the garment.

Seam allowances of front and back pieces extend past edges of stabilizer.

---

### **Step 3 — Allowances**

On front and back, clip side seam allowances at markings.

---

### **Step 4 — French seams**

Sew shoulder seams and side seams above markings as French seams (double seams): First lay the fabric pieces wrong sides facing and stitch the 1.5 cm (5/8 in) wide seam allowances together, 7 mm (1/4 in) from edge. Press seam allowances open. Then lay pieces right sides facing, with the seam exactly along the fold. Now stitch along marked seam line, 8 mm (a generous 1/4 in) from fold edge. Press seam allowances to one side.

---

### **Step 5 — Neck, armholes and hem**

Trim away allowances on neck edge, armholes, and hem edges.

---

## **Step 6 — Bias tape**

Fold pre-folded bias tape in half lengthwise and press. Lay bias tape over neck edge and baste. Turn in end which lies on top at one shoulder seam. Edgestitch bias tape in place. Bind edges of armholes, turning in end of tape which lies on top at the side seam. Bind hem edges, turning in both ends of bias tape.

---

## **Step 7 — Rinse**

Rinse in cold water to remove the stabilizer.

---

**BurdaStyle**

07/2011 Net top