

10/2011 Ankle-length double breasted wool coat

By: burda style magazine

<http://www.burdastyle.com/projects/102011-ankle-length-double-br>



Long wool coat burda style magazine patterns FAQ

Materials

Twill weave wool

Step 1 — Preparation



Paper cut for ANSI A (German DIN A4) prints:

This pattern is printed on 8.5 × 11 sheets of plain paper. Do not scale or center pages before printing. Wait until all sheets are printed out before beginning to tape them together. **Do not cut out pattern pieces yet**— Arrange the sheets on a large, hard, flat surface so that they fit together, matching up like numbers and letters (i.e. 6A to 6A). To tape pattern together, fold under the margin of one piece (6A) and tape right against the line of it's matching number/letter (6A).

burda style magazine pattern do not have seam allowance included.

Seam and hem allowances to be added: Seams and edges 1.5 cm (5/8 in).

Step 2 — Cutting out



Twill weave wool:

1 centre front 2x

2 side front 2x

3 upper centre back 2x

4 lower centre back 2x

5 side back 2x

6 upper sleeve 2x

7 under sleeve 2x

8 collar, on a fold 2x

9 collar band, on a fold 2x

10 front facing 2x

11 back facing, on a fold 1x

12 pocket 2x

Lining: piece 1 to lining line; piece 3 minus width of facing and with an ease pleat of approx. 2 cm (3/4 cm) at centre back; pieces 2, 4, 5, and 6; and piece 12 minus width of facing.

Interfacing: See pattern layout. Also interface hem allowances.

Step 3 — Darts

Stitch the darts in centre front pieces. Cut the darts along centre and press open, pressing points of darts flat.

Step 4 — Center back seam

Stitch the upper centre back pieces to the lower centre back pieces. Press the seam allowances open. Stitch the centre back seam, leaving the vent open. At top of vent, clip diagonally into corner of seam allowance on right centre back. Press the seam allowances open and press allowances on edges of vent onto left back. Press allowance on vertical edge of underlap to the inside and stitch. Topstitch left centre back diagonally at top of vent, as marked, catching underlap.

Step 5 — Seams

Stitch the front and back section seams, side seams, shoulder seams, and facing seams.

Step 6 — Patch pockets

Stitch pocket lining pieces to self-facings of pockets, leaving approx. 5 cm (2 ins) open in centre of seam, for turning. Turn facings and lining to outside and stitch to side and lower pocket edges. Turn pockets right side out and sew openings closed. Pin pockets to coat, at abutting lines, and sew in place by hand.

Step 7 — Notched collar

Stitch the collar band pieces to the collar pieces. Trim the seam allowances and press allowances open. Topstitch close to each side of seams. Stitch the collar pieces together along outer edges, building a little extra fullness into the top collar piece. Begin and end stitching exactly on seam line of joining edge. Turn the collar right side out. Pin the facings right sides together with the jacket. Pin fold lines of lapels together. Pin the upper edges together at the marking (seam number 5). Build a little extra fullness into corners of lapels. Stitch along front edges and edges of lapels, up to marking. Clip the seam allowances of the fronts and facing at marking, close to end of stitching. Leave the facings lying right sides together with the jacket for now. Lay the collar between the jacket and facing. Stitch the under collar with collar band to the neck edge of the jacket, from each marking to the corner. Clip seam allowances of the fronts onto corners. Stitch the long edge of the under collar to the neck edge of the jacket. Stitch the top collar with the collar band to facing, clipping the seam allowance of the facing into corner. Press allowances of collar joining seams open. Turn facing to inside. Pin the collar joining seams together exactly. Turn back facing up and stitch seam allowances together, close to collar joining seam. Turn facing down again.

Step 8 — Hem facings

Unfold facings at hem. Press the hem allowance to the inside and sew in place by hand. Topstitch 1.5 cm (5/8 in) from hem edge. Turn the facings to the inside.

Step 9 — Sleeves

Stitch the sleeve seams. Press the sleeve hem allowances to the inside and sew in place by hand.

Step 10 — Sleeve caps

Set in sleeves, easing sleeve caps.

Step 11 — Construct lining

On the centre back lining pieces, stitch the allowances of the centre seam together, 1 cm (3/8 in) from edge. For the ease pleat, stitch along centre back at top and bottom (above vent), each approx. 5 cm (2 ins) long, and baste in between. Press pleat and vent allowances to one side, as mirror image of outer fabric. Stitch seams of lining. Set in the sleeve linings.

Step 12 — Line coat

Stitch lining to inside edge of facing, leaving approx. 8 cm (3 1/4 ins) open at the bottom. Lay the lining inside the coat with wrong sides facing, pulling linings into sleeves. Pin a fold, approx. 1 cm (3/8 in) deep, in the lining, above coat hem and sleeve hems. Turn in the lining and sew to hem allowance by hand. Lay extra length of lining down, and press lightly. At the back vent, turn in the lining at underlap edge of the right back and pin in place. Trim the other edge of lining to 1 cm (3/8 in) before hemmed edge of underlap. Clip 1 cm (3/8 in) diagonally into top corner. Turn in edge of lining and pin to the vent facing of the left back. At the top of the vent, turn in the lining and pin to the underlap. At back vent, sew lining to vent facing and to edge of underlap. Sew remaining front edges of lining in place. Turn in sleeve linings and sew to hem allowances. Lay extra length down and press.

— Topstitch 1 cm (3/8 in) from front edges and edges of lapels and collar.

Step 13 — Buttonholes

Work buttonholes in right front. Work top buttonhole for inside button in left front.

BurdaStyle

10/2011 Ankle-length double breasted wool coat