

01/2012 Panties

By: burda style magazine

<http://www.burdastyle.com/projects/012012-panties>



Panties burda style magazine patterns FAQ

Materials

Cotton satin with crosswise stretch

Step 1 — Preparation




Paper cut for ANSI A (German DIN A4) prints:

This pattern is printed on 8.5 × 11 sheets of plain paper. Do not scale or center pages before printing. Wait until all sheets are printed out before beginning to tape them together. **Do not cut out pattern pieces yet**— Arrange the sheets on a large, hard, flat surface so that they fit together, matching up like numbers and letters (i.e. 6A to 6A). To tape pattern together, fold under the margin of one piece (6A) and tape right against the line of it's matching number/letter (6A).

burda style magazine pattern do not have seam allowance included.

Seam and hem allowances to be added: Seams and edges 1.5 cm (5/8 in).

Step 2 — Cutting out



Satin:

21centre front piece , on a fold 1x

22side front piece 2x

23back piece, on a fold 1x

Cotton jersey:

21facing, on a fold 1x

Step 3 — Tulle pieces

Baste pieces of tulle to corresponding satin pieces, with wrong side facing right side. Treat these pieces as one layer of fabric from now on.

Step 4 — Facing

Neaten upper narrow edge of facing with an overlockstitch, thereby trimming away seam allowance. Lay facing on centre front panty piece, wrong sides together, and baste to side and lower edges.

Step 5 — Seam allowances

Stitch the side front panty pieces to the centre front panty piece (seam number 1). Trim the seam allowances to 7 mm (1/4 in) wide, neaten edges together, and press toward the centre. Stitch the right side seam. Press the seam allowances open.

Step 6 — Lace trim

Pin the lace trim to the upper edge of the panties so that the scalloped edge lies on garment piece, 5 mm (3/16 in) past seam line. Stitch lace edging in place, 5 mm (3/16 in) from edge. Turn allowance to inside — scalloped edge of lace extends. Topstitch close to upper edge of panties.

Step 7 — Zip

Sew invisible zip to left opening edges, see — Helpful Hint— on page 12. Leave zip tapes extending at upper edge of panties. Stitch left side seam from lower edge to zip. Turn in top ends of zip tapes and sew to upper edge, together with seam allowances.

Step 8 — Crotch

—Stitch crotch seam (seam number 3). Press allowances onto back.

Step 9 — Bias strip

Fold bias strips for leg opening edges in half lengthwise and press, right side facing out. Pin each folded strip to leg opening edge so that fold edge of strip lies on garment piece, 1 cm (3/8 in) past seam line. Turn in ends of each strip at crotch seam. Stitch along lines of leg openings. Trim seam allowances. Turn bias strips to inside. Press edges and topstitch 7 mm (1/4 in) from edges. Pull 5 mm (3/16 in) wide elastic into leg edges. Sew ends of each elastic together for circumference of 49 — 51 — 53 — 55 — 57 cm (19 1/4 — 20 1/4 — 21 — 21 3/4 — 22 1/2 ins).

Step 10 — Ribbon

Cut 15 cm (6 ins) of satin ribbon, tie in a bow, and sew to upper edge of panties, at centre front.

BurdaStyle

01/2012 Panties