6/2010 One Shoulder Ruffle Blouse

By: burda style magazine

http://www.burdastyle.com/projects/62010-one-shoulder-ruffle-blou

One Shoulder Ruffle Blouse burda style magazine patterns FAQ

Materials

Silk satin

Step 1 — Preparation



Trace the pattern pieces from the pattern sheet.
Seam and hem allowances:
Seams and edges 1.5 cm (5/8 in), hem 3 cm (1 1/4 ins).

Step 2 — Cutting Out



Satin:
1 front 1x
2 back 1x
a) bottom frill, a total of 164 â— 170 â— 176 â— 182 â— 188 â— 194 cm (64 1/2 â— 67 â— 69 1/4 â— 71 3/4 â— 74 â— 76 1/2 ins) long, 17 cm (6 3/4 ins) wide,
b) top frill, a total of (64 1/2 â— 67 â— 69 1/4 â— 71 3/4 â— 74 â— 76 1/2 ins) long, 12 cm (4 3/4 ins) wide,
c) bias strip for neck edge, 84 â— 86 â— 89 â— 91 â— 94 â— 97 cm (33 â— 34 â— 35 â— 36 â— 37 â— 38 1/4 ins) long, 4 cm (15/8 ins) wide (incl. allowance), d) bias strip for left armhole, 47 â— 49 â— 50 â— 52 â— 54 â— 55 cm (18 1/2 â— 19 1/4 â— 19 3/4 â— 20 1/2 â— 21 1/4 â— 21 3/4 ins) long, 4 cm (1 5/8 ins) wide (incl. allowance).

Step 3 — Right side seam and left shoulder seam

Stitch right side seam and left shoulder seam. Trim seam allowances to 7 mm (1/4 in) wide, neaten together and press onto back.

Step 4 — Neck edge

Fold bias strip for neck edge lengthwise and press, right side facing out. Pin doubled bias strip to neck edge so that fold edge of strip lies on garment piece, 1 cm (3/8 in) past seam line. Turn back end of strip which lies underneat and lay other end over it. Stitch along seam line. Trim seam allowances. Lay bias strip to inside and press edge. Topstitch 7 mm (1/4 in) from neck edge.

Step 5 — Bias strip

Face edge of left armhole with the doubled bias strip as for neck edge. Do not turn in ends of strip.

Step 6 — Frill piece

Stitch ends of each frill piece together.

Step 7 — Neaten lengthwise edges of frills with closely spaced zigzag stitching

Press allowance to wrong side of fabric. Work from right fabric side to stitch along fold edge with short, closely spaced zigzag stitching. Trim allowance on inside close to stitching.

Step 8 — Top frill and bottom frill

Lay top frill on bottom frill, with wrong side facing right side. Baste upper edges of frills together and gather to fit neck edge by stitching two lines of machine basting (longest stitch setting), 1.5 cm (5/8 in) and 2 cm (3/4 in) from upper edge of frill. Stitch frill to neck edge, between lines of gathering so that upper edge of frill extends by 1.5 cm (5/8 in).

Step 9 — Invisible zip and left side seam

Sew invisible zip to left opening edge. Begin at marked hem line. The zip should open from the hem edge, up. Stitch left side seam from upper edge to zip. Sew upper ends of seam allowances in place.

Step 10 — Hem casing

Lay hem allowance to inside, turn in, and stitch 1.5 cm (5/8 in) from fold to form elastic casing. Insert elastic and stitch ends together for a finished circumference of 80 â— 84 â— 88 â— 92 â— 96 â— 100 cm (31 1/2 â— 33 â— 34 3/4 â— 36 1/4 â— 37 3/4 â— 39 1/2 ins).

BurdaStyle

6/2010 One Shoulder Ruffle Blouse