

09/2011 Animal print trousers

By: burda style magazine

<http://www.burdastyle.com/projects/092011-animal-print-trousers>



Animal print trousers burda style magazine patterns FAQ

Materials

Cotton gabardine with crosswise stretch

Step 1 — Preparations



Paper cut for ANSI A (German DIN A4) prints:


This pattern is printed on 8.5 × 11 sheets of plain paper. Do not scale or center pages before printing. Wait until all sheets are printed out before beginning to tape them together. **Do not cut out pattern pieces yet**— Arrange the sheets on a large, hard, flat surface so that they fit together, matching up like numbers and letters (i.e. 6A to 6A). To tape pattern together, fold under the margin of one piece (6A) and tape right against the line of it's matching number/letter (6A).

burda style magazine pattern do not have seam allowance included.

Seam and hem allowances to be added: Seams and edges 1.5 cm (5/8 in).

see example here: <http://www.burdastyle.com/projects/072011-jumpsuit/instructions/1>

Step 2 — Cutting out



Views A, B, C:

21 front trouser piece 2x

22 large pocket piece 2x

23 back trouser piece 2x

24 side piece 2x

25 front waistband, on a fold 2x

26 back waistband 4x

Contrasting fabric, view C only:

27 front turn-up facing 2x

28 back turn-up facing 2x

Lining A, B, C:

29 small pocket piece 2x

Interfacing: See pattern layout. Interface outer waistband pieces.

Step 3 — Stretch seam edges

Lay back trouser pieces right sides together. Press inside leg seam edges above marking with a steam iron or under a damp cloth and stretch until they match corresponding edges of front trouser pieces.

Step 4 — Side pieces

Stitch side pieces to back trouser pieces. Press seam allowances open. Stitch side seams, but do not stitch across pocket openings. Press seam allowances open.

Step 5 — Inseam pockets

Pin the pocket pieces right sides together with the seam allowances of pocket opening edges — pocket lining pieces in front, fabric pocket pieces in back. Stitch pocket pieces in place along marked seam lines — above pocket openings, stitch pocket pieces close to seam. Press pocket pieces forward and stitch together. Baste to wrong side of front trouser pieces.

Step 6 — Leg seams

Stitch inside leg seams. Pull one trouser leg into the other, with right sides facing. Stitch front and back centre seam as continuous seam, ending stitching in back approx. 5 cm (2 ins) before the slit mark.

Step 7 — Waistband

Stitch side seams on waistband pieces. Stitch interfaced outer waistband unit to upper edge of trousers. Press seam allowances of joining seam onto waistband.

Step 8 — Zip

Sew invisible zip to slit edges, from upper edge of waistband to slit mark. Stitch remainder of centre back seam, to zip.

Step 9 — Seam allowances

Lay inside waistband piece right sides together with attached waistband piece and pin the upper edges together. At zip opening, turn ends of the inside waistband back, 5 mm (3/16 in) before edge of opening, and pin to upper edge. Turn slit allowances of outer waistband piece to outside and pin to upper edge, over inside waistband piece. Stitch along upper edge. Turn allowances of slit edges to inside. Turn inside waistband up and stitch to seam allowances, as far as possible, close to seam. Turn inside waistband to inside and baste over joining seam, not turning edge under. Sew to zip tapes. Work from right side of garment to stitch along line of joining seam, thereby catching side edge of waistband.

Step 10 — Turn-ups

Press edges of trouser legs to inside on turn-up fold lines. Stitch by machine or sew by hand. Fold lower edges of trouser legs up to abutting lines and press. Sew turn-ups to seams, with a few stitches by hand.

BurdaStyle

09/2011 Animal print trousers