

07/2010 Slim Fit Striped Trousers

By: burda style magazine

<http://www.burdastyle.com/projects/072010-slim-fit-striped-trousers>

Slim Fit Striped Trousers burda style magazine patterns FAQ

Materials

gabardine with lengthwise stripes


Step 1 — Preparation

Trace pattern pieces from the pattern sheet. Note different grain lines and details for views A, B and C. The stitching line at the zip opening is marked for size 34. For sizes 36 — 44, mark the stitching line the same distance from centre front as for size 34, noting length of opening.

Seam and hem allowances:

Seams and edges 1.5 cm (5/8 in), hem 3 cm (1 1/4 ins).

Step 2 — Preparation



1 front trouser piece 2x

2 pocket piece 2x

3 side hip yoke with

integrated pocket piece 2x

4 centre back trouser piece 2x

5 side back trouser piece 2x

6 back yoke 2x

7 front waistband 4x

8 back waistband 4x

a) right facing piece, 16 1/2— 16 1/2— 16 1/2— 16 1/2— 18 1/2— 18 cm (6 3/8 1/2— 6 3/8 1/2— 6 3/8 1/2— 6 3/8 1/2— 7 1/2— 7 ins) long, 4 cm (1 5/8 ins) wide,

b) left underlap piece, 16 1/2— 16 1/2— 16 1/2— 16 1/2— 18 1/2— 18 cm (6 3/8 1/2— 6 3/8 1/2— 6 3/8 1/2— 6 3/8 1/2— 7 1/2— 7 ins) long, 6 cm (2 1/2 ins) wide, finished width 3 cm (1 1/4 ins), c) 5 belt carriers, a total of 35 cm (13 3/4 ins) long, 4 cm (1 5/8 ins) wide (incl. allowance).

Interfacing: Iron onto outer waistband pieces.

Step 3 — Hip yoke pockets

Stitch pocket pieces right sides together with pocket opening edges of front trouser pieces. Lay pocket pieces up and stitch to seam allowances, close to seam. Turn pocket pieces to inside. Pin pocket opening edges to side hip yokes at placement lines. Stitch pocket pieces together. Baste pocket pieces to wrong side of front trouser pieces. Topstitch close to pocket opening edges and again 7 mm (1/4 in) from these edges.

Step 4 — Back

Stitch back section seams (seam number 2). Press seam allowances onto centre trouser pieces. Topstitch close to seams.

Step 5 — Stretch seam edges

Lay back trouser pieces right sides facing. Stretch inside leg edges above marking by pressing with a steam-iron or under a damp cloth until they are the same length as corresponding edge on front trouser piece.

Step 6 — Back yokes

Stitch back yokes to back trouser pieces. Topstitch yokes close to seams and again 7 mm (1/4 in) from seams.

Step 7 — Side seams

Stitch forwarded side seams. Topstitch trouser backs close to seams.

Step 8 — Inside leg seams

Stitch inside leg seams. Press seam allowances open. Stitch centre front seam from slit mark to inside leg seam.

Step 9 — Zip opening

Stitch right facing piece right sides together with right edge of opening. Turn facing to inside, press edge, and topstitch close to edge. Press allowance on left edge of opening (underlap) to inside, 5 mm (3/16 in) before centre front. Stitch zip under edge, stitching close to teeth of zip. Pin opening closed, matching centres. Stitch free zip tape to right facing, not catching trouser piece. Baste facing in place. Topstitch opening from upper edge to the end, as marked. Also topstitch 7 mm (1/4 in) from this line of topstitching. Fold underlap piece lengthwise and stitch across bottom end. Turn right side out. Lay underlap under left edge of opening and pin to allowance. Stitch allowance of opening edge to underlap, close to zip joining seam. Close zip. Topstitch to end of opening, catching underlap.

Step 10 — Center back seam

Stitch centre back seam. Press seam allowances open from upper edge to beginning of curve. Do not press allowances flat along curve.

Step 11 — Belt carriers

Fold strip for belt carriers lengthwise, right side facing in. Stitch 1.2 cm (1/2 in) from fold edge. Turn right side out. Topstitch close to edge. Cut into 5 pieces. Baste belt carriers to upper edge of trousers, in front placing one next to each pocket opening and in back placing one 8 cm (3 1/4 ins) from each side seam and one at centre back.

Step 12 — Waistband

Stitch centre back seam and side seams on waistband pieces. Stitch interfaced waistband unit to upper edge of trouser, with right end of waistband extending from centre front and stitching left end of waistband to underlap. Press seam allowances onto waistband. Lay inside waistband unit right sides together with attached waistband unit. Stitch across ends of waistband and along upper edge of waistband, stitching right end of waistband along centre front. Trim seam allowances, trimming corners diagonally. Turn waistband right side out. Turn in inside edge of waistband in front, about 5 cm (2 ins) long, and sew in place, then lay flat over joining seam (not turned in) and baste. Work from right side to stitch along line of joining seam, catching inside edge of waistband. Also topstitch waistband close to all edges. Work buttonhole in right end of waistband.

Step 13 — Belt carriers

Fold strip for belt carriers lengthwise, right side facing in. Stitch 1.2 cm (1/2 in) from fold edge. Turn right side out. Topstitch close to edge. Cut into 5 pieces. Baste belt carriers to upper edge of trousers, in front placing one next to each pocket opening and in back placing one 8 cm (3 1/4 ins) from each side seam and one at centre back.

BurdaStyle

07/2010 Slim Fit Striped Trousers