

10/2011 Houndstooth Bell Bottoms

By: burda style magazine

<http://www.burdastyle.com/projects/102011-houndstooth-bell-bottoms>




Wide leg trousers sizes: 36-42 burda style magazine patterns FAQ

Materials

Main fabric: size 36, 38, 40: 150 cm (59 in) wide and 1,60 m (1 3/4 yds) long size 42, 44: 150 cm (59 in) wide and 2,20 m (2 1/2 yds) long Lining (for pocket pieces): approx. 40 × 30 cm (16 × 12 ins) Waistband interfacing: Finished width of waistband 2,5 cm (1 in) Zipper: size 36,38,40: 16 cm (6 1/2 in) size 42,44: 18 cm (7 in)

Step 1 — Preparation



Paper cut for ANSI A (German DIN A4) prints:


This pattern is printed on 8.5 × 11 sheets of plain paper. Do not scale or center pages before printing. Wait until all sheets are printed out before beginning to tape them together. **Do not cut out pattern pieces yet**— Arrange the sheets on a large, hard, flat surface so that they fit together, matching up like numbers and letters (i.e. 6A to 6A). To tape pattern together, fold under the margin of one piece (6A) and tape right against the line of it's matching number/letter (6A).

Trace the pattern pieces from the pattern sheet in your size. This pattern runs in the sizes 36, 38, 40, 42 and 44.

burda style magazine pattern do not have seam allowance included.

Seam and hem allowances to be added: Seams and edges 1.5 cm (5/8 in).

Step 2 — Cutting out



Main fabric:

Pattern piece number 21 – front pant piece, cut x 2

from this piece also draft and cut the pocket piece x2

and the left underlap piece(for zipper):

size 36,38,40: 17 cm (6 3/4 in) long and 5 cm (2 in) wide, finished width 2,5 cm (1 in)

Pattern piece number 22 – back pant piece, cut x2

Also draft and cut the following pieces, not on the pattern sheet,

a) right waistband:

size 36: 34,5 cm (13 3/8 in) long x 5 cm (2 in) wide

size 38: 36,5 cm (14 3/8 in) long x 5 cm (2 in) wide

size 40: 38,5 cm (15 1/4 in) long x 5 cm (2 in) wide

size 42: 40,5 cm (16 in) long x 5 cm (2 in) wide

size 44: 42,5 cm (16 3/4 in) long x 5 cm (2 in) wide

b) left waistband, (with 3 cm underlap included):

size 36: 37,5 cm (14 3/4 in) long x 5 cm (2 in) wide

size 38: 39,5 cm (15 5/8 in) long x 5 cm (2 in) wide

size 40: 41,5 cm (16 3/8 in) long x 5 cm (2 in) wide

size 42: 43,5 cm (17 1/8 in) long x 5 cm (2 in) wide

size 44: 45,5 cm (18 in) long x 5 cm (2 in) wide

finished width for waistband will be 2,5 cm (1 in). (Don't forget to also add seam allowances for these pieces.

Lining:
pocket piece x2

Interfacing:
Cut for and iron onto wrong side of waistband pieces.

Step 3 — Darts

Stitch darts in front and back trouser pieces. Press toward centre.

Step 4 — Front creases

Fold front trouser pieces lengthwise, wrong side facing in, and press creases.

Step 5 — Side seams

Lay front pieces with right side facing in together with back pieces and pin and stitch along side seams, but do not stitch across pocket opening.

Step 6 — Inseam pockets

Pin pocket pieces right sides together with seam allowances of pocket opening edges — pocket lining pieces in front, fabric pocket pieces in back. Stitch pocket pieces in place, close to side seam and along seam line at pocket openings. Press seams open, pressing pocket pieces apart. Topstitch front pocket opening edges as marked. Press back pocket pieces forward. Stitch pocket pieces together. Tack upper pocket edges to wrong side of trouser fronts.

Step 7 — Slit

Stitch inside leg seams. Stitch centre front seam, from slit mark to inside leg seam.

Step 8 — Zipper opening

Press self-facings on opening edges to inside. On right edge, stitch along centre front. On left edge, stitch 5 mm (3/16 in) before centre front. Stitch zipper under left edge of opening (underlap), close to teeth of zipper. Pin opening closed, matching centre fronts. Stitch loose zipper tape to right facing, not catching pant piece. Tack facing in place. Topstitch opening from top to 3 cm (1 1/4 ins) before end, as marked. Fold underlap piece lengthwise. Stitch across bottom end. Turn right side out. Lay underlap under left opening edge and pin to facing. Stitch facing to underlap, close to zipper joining seam. Lay opening closed again and topstitch to the end, catching underlap.

Step 9 — Waistband and centre back seam

Stitch right and left waistband to upper trouser edges, stitching waistband underlap to opening underlap. Press seam allowances of joining seams onto waistband pieces. Stitch centre back seam, stitching ends of waistband together. Press seam allowances open from upper edge to beginning of curve. Do not press seam allowances flat along curve. Fold waistband lengthwise, right side facing in. At ends of waistband, turn allowance on inside edge up. Stitch across ends. Turn right side out. At ends of waistband, turn inside edge

under, approx. 4 cm (15/8 ins) long, and tack. Then lay remaining edge flat over joining seam. Work from right side to stitch along line of joining seam. Work a buttonhole in right end of waistband. Sew button to left end.

Step 10 — Hem

Fold hem allowances to inside, press and stitch in place by hand.

Step 11 — Creases

Press creases in trouser backs. Press creases in front hem edges.

BurdaStyle

10/2011 Houndstooth Bell Bottoms